

# Linux - How to Decrease an LVM Partition

**Note:** In this example we are working in CentOS 7, some commands may differ in different Linux distributions. As of CentOS 7 the default file system is XFS which is not currently possible to shrink, this example is working with the ext4 file system.

In this example we will work through shrinking logical volume `/var/centos/var` from 10GB to 5GB.

## Overview of Logical Volume Manager (LVM)

Before working through the resizing process it's important you first understand some basic concepts around physical volumes, volume groups, logical volumes, and the file system.

- **Physical Volume (PV):** This can be created on a whole physical disk (think `/dev/sda`) or a Linux partition.
- **Volume Group (VG):** This is made up of at least one or more physical volumes.
- **Logical Volume (LV):** This is sometimes referred to as the partition, it sits within a volume group and has a file system written to it.
- **File System:** A file system such as ext4 will be on the logical volume.

## LVM Resize – How to decrease or shrink the logical volume

To decrease the size of an LVM partition you must first decrease the file system within in order to avoid possible data corruption. As there is the potential for this to happen if you enter the command incorrectly, it is strongly recommended that you have a full backup of your data before proceeding. Shrinking a logical volume will give you more space in the volume group, meaning that you could instead [extend another logical volume](#) with this new found space.

The first step will depend on if you're looking to shrink a LVM root volume, or non-root volume.

## Shrinking a root volume

The root volume would typically be the logical volume that is mounted to /. You cannot unmount this to shrink it as it's in use by the running operating system meaning that you will have to first boot from a Live CD to complete this. Once booted into the Live CD, you may first need to run the below command to pick up LVM volumes, however this usually happens during boot so may not be required, if in doubt just run it.

```
vgchange -a y
```

## Shrinking a non-root volume

Alternatively if the volume you are shrinking is a non-root volume, that is any other volume not mounted to the root of the file system, you can unmount the volume as shown below to proceed. Please note that when you unmount the volume the data will not be available, so you may need to schedule down time and stop running applications that use data from it prior to unmounting. Unmount by specifying either the logical volume or the location it's currently mounted to, in the below example we specify the logical volume which can be found in /dev/(vg-name)/(lv-name).

```
umount /dev/centos/var
```

**All following steps now apply to both a root or non-root volume.**

Before being able to attempt to shrink the size of an LVM volume, you must first run a file system check on it. If you don't do this, you will get an error message and will not be able to proceed. This is a required step as resizing a file system in a bad state could cause data corruption. The -f flag makes the check run even if the file system appears clean, while -y assumes yes to all questions and will respond if asked to fix a problem.

```
e2fsck -fy /dev/centos/var
```

Next you need to shrink the file system, to be safe we're going to shrink the file system lower than what the logical volume will shrink to. This is because we don't want to accidentally shrink the logical volume to a size lower than the file system in the next step, as this can result in corruption and data loss. Don't worry, we'll reclaim the space at the end.

The command below will shrink the file system so that it is only 4G in size total, note that whatever size you specify to shrink to you must have in free space within the file system otherwise you must first delete data.

```
resize2fs /dev/centos/var 4G
```

Once the file system has been reduced, we can shrink the size of the logical volume with the `lvreduce` command. Reduce this to the size that you want the volume to be, as specified by the `-L` flag. Instead if you want to reduce by a specified size, simply put a `-` in front of the size. Both are shown below for completeness, however you only need to run one.

To reduce to 5G

```
lvreduce -L 5G /dev/vg/disk-name
```

To reduce by 5G

```
lvreduce -L -5G /dev/vg/disk-name
```

Once you execute the `lvreduce` command you will get a warning advising the size you have chosen to reduce to so use this as a chance to confirm you're shrinking the logical volume to a size that is NOT smaller than the size you previously shrunk the file system to. Once you have confirmed it's fine to proceed enter `'y'` and press enter.

After the logical volume has been lowered to the required size, run `resize2fs` on the volume as this will extend the file system to use all available space within the logical volume. This makes use of all remaining free space so that none is wasted from when we previously shrunk the file system to a lower size than the logical volume.

```
resize2fs /dev/centos/var
```

At this point all that's left to do is mount the volume. If this was a root volume and you're working within a Live CD, simply boot back into your primary Linux operating system.

If this was a non-root volume and you unmounted it to complete the reduction, simply mount it back. You can do this with `'mount -a'` assuming you have the configuration already set in `/etc/fstab`, otherwise specify the logical volume and where it should mount to. Here we're manually mounting to `/mnt` just for testing.

```
mount /dev/centos/var /mnt
```

After you've either booted back to primary operating system or completed the mount, check the space shown with the `'df'` command to confirm it has been decreased as expected.

```
[root@CentOS7 /]# df -h
Filesystem      Size  Used Avail Use% Mounted on
/dev/mapper/centos-root 9.8G  1.4G  8.5G  14% /
devtmpfs        908M   0  908M   0% /dev
```

tmpfs	914M	0	914M	0%	/dev/shm
tmpfs	914M	8.6M	905M	1%	/run
tmpfs	914M	0	914M	0%	/sys/fs/cgroup
/dev/sda1	497M	96M	402M	20%	/boot
/dev/mapper/centos-var	4.8G	20M	4.6G	1%	/mnt

In this example `/dev/centos/var` is correctly showing as shrunk down from the original 10G.

Revision #2

Created 2 September 2024 19:28:47 by Steve Ling

Updated 14 September 2024 17:21:55 by Steve Ling