

Kiwiplan - Box Plant Classic/Refresh To VUE Master Parameters

Master Data Parameters for a Classic Refresh Plant

This is used to know where the parameter take affect in either VUE or Classic

ReFresh				
Setup In				
Classic	VUE	Option	Vue Script	Comments
	Yes	Material > Material Group > Board Group		
	Yes	Configuration > Organization > Score Types		Make sure default in VUE is set but also set CORR-CP & PCS-QB
Yes	Yes	Configuration > Organization > Score Types & PCS-QB & CORR-CP		Make sure that classic has the default converting score set
	Yes	Materials > Flute Types		
	Yes	Materials > Material Group > Board Group		
	Yes	Materials > Material Groups > Paper Classes		
Yes	Yes	CSC00 > P > CSC > UD		

	Yes	Configuration > Downtime > Downtime Classes		
Yes	Yes	Materials > Materials > Shippers & GEN-SN		VUE only needed for COMMS. Classic for everything else
Yes		PCS00 > P > GEN > TB		
Yes		PCS00 > P > GEN > TU		
Yes	Yes	Configuration > Parameters > Manufacturing > COMMS & GEN-UM		
Yes		GEN-UP		Not used in VUE but stored on the unitising table
Yes		PCS00 > P > GEN > WC		
Yes		INV-SM		Not used in VUE but stored on the shipmethod and job table
Yes		PCS00 > P > PCS > CC	Yes	
Yes		PCS00 > P > PCS > CE	Yes	
Yes		PCS-CN, GEN-CM, GEN-CN		
	Yes	Configuration > Parameters > PCS > Feedback		
Yes		PCS00 > P > PCS > IC	Yes	
Yes		Configuration > Tool > Tool Types & PCS- PD		VUE needs these for tooling but ESP reads classic for type
Yes		PCS00 > P > PCS > QD		
Yes		PCS00 > P > PCS > QS		
Yes		Configuration > Organization > Machine Groups & PCS-QE		Classic & ESP reads the group description from classic

Yes		Configuration > Machine > Machine Operations & PCS-QK		
Yes		Configuration > Order > Hold Statuses		
Yes		Configuration > Order > Hold Statuses		
Yes		PCS00 > P > PCS > QP		
Yes		Configuration > Machine > Slot WidthCodes		
Data Fields				
	Yes	Materials > Materials > Papers		
	Yes	Materials > Materials > Starch		
	Yes	Materials > Materials > Corrugated Boards		
	Yes	Materials > Materials > Corrugator Coatings		
Yes		PCS00 > L > D		
		Materials > Material Group > Ink Groups		
Yes		Configuration > Organization > Plant > Stores and invmenu		Only machine in and out feed locations need to be in VUE
Yes		Configuration > Organization > Plant > Stores and invmenu		Only machine in and out feed locations need to be in VUE
Yes	Yes	Configuration > KDG Templates & lbs00:A		Just code needs to exist in classic, label defined in VUE
	Yes	Configuration > Organization > Plant > Machines		
		Calendars > Shift Names		
		Calendars > Calendars		

		PICS and ESP		Must enter in ESP and PICS and must match
--	--	--------------	--	---

Revision #1
Created 31 January 2025 00:09:42 by Steve Ling
Updated 31 January 2025 00:25:21 by Steve Ling