

Linux

Copyright Notice

SFL Services LLC has prepared this document for use only by their staff, agents, customers and prospective customers. Companies, names and data used as examples in this document are fictitious unless otherwise noted. No part of this document may be reproduced or transmitted in any form or by any means, electronic or mechanical, for any purpose, without the express written permission of SFL Services LLC, who reserve the right to change specifications and other information contained herein without prior notice. The reader should consult SFL Services LLC to determine whether any such changes have been made.

Licensing and Warranty

The terms and conditions governing the licensing of SFL Services LLC software consist solely of those set forth in the written contracts between SFL Services LLC and its customers. Except as expressly provided for in the warranty provisions of those written contracts, no representation or other affirmation of fact contained in this document, including but not limited to statements regarding capacity, suitability for use or performance of products described herein, shall be deemed to be a warranty by SFL Services LLC for any purpose, or give rise to any liability of SFL Services LLC whatsoever.

Liability

In no event shall SFL Services LLC be liable for any incidental, indirect, special or consequential damages whatsoever (including but not limited to lost profits) arising out of or related to this document or the information contained in it, even if SFL Services LLC had been advised, knew or should have known of the possibility of such damages, and even if they had acted negligently.

- [Linux - Setting up a Logging Server](#)
- [Linux - Bag of Tricks](#)
- [Linux - How to Decrease an LVM Partition](#)
- [Linux - Increase the size of a LVM Partition](#)
- [Linux - Setting up an SSL secured Webserver with CentOS](#)
- [Linux - Samba Setup Rocky 9](#)
- [Linux - Setup Rocky 9 SMTP Server](#)

Linux - Setting up a Logging Server

Summary

This is to setup a logging server to capture logs from any servers on your network.

Prerequisites

Install of a RedHat or Rocky Linux minimal install

Configuration

You will need to edit the file `/etc/rsyslog.conf`

Editing the file

```
vi /etc/rsyslog.conf
```

You will need to change to the following to allow port 514 to be open

```
# Provides UDP syslog reception
# for parameters see http://www.rsyslog.com/doc/imudp.html
module(load="imudp") # needs to be done just once
input(type="imudp" port="514")

# Provides TCP syslog reception
# for parameters see http://www.rsyslog.com/doc/imtcp.html
module(load="imtcp") # needs to be done just once
input(type="imtcp" port="514")
```

Then simply restart the rsyslog daemon

```
systemctl restart rsyslog
```

Multi Host Logging to one server

```
vi /etc/rsyslog
```

Add the following

Before this entry "#### RULES ####"

```
$template RemoteLogs,"/var/log/%HOSTNAME%/%PROGRAMNAME%.log"  
. ?RemoteLogs
```

This will enable for all host/servers to log to their own folders

The entry should look like this

```
# Provides TCP syslog reception  
# for parameters see http://www.rsyslog.com/doc/imtcp.html  
module(load="imtcp") # needs to be done just once  
input(type="imtcp" port="514")  
  
#custom  
$template RemoteLogs,"/var/log/%HOSTNAME%/%PROGRAMNAME%.log"  
*,* ?RemoteLogs  
& ~  
  
#### RULES ####
```

The directive `$template` tells , rsyslog daemon to gather and write all of the received remote messages to separate logs under `/var/log`, based on the hostname (client machine name) and remote client facility (program/application) that generated the messages as defined by the settings present in the template `RemoteLogs`. The second line `"*,* ?RemoteLogs"` means record messages from all facilities at all severity levels using the `RemoteLogs` template configuration. The third lines makes the append happen.

Setup Host Servers

This is what to setup on the servers you wish to log to one server

You must login to the server and then edit the following file

```
vi /etc/rsyslog.conf
```

Once opened you have to add at the end of the file the following to log everything

```
*,* @192.168.253.86:514 # use @ for UDP Protocal
*,* @@192.168.253.86:514 # use @@ for TCP Protocal
```

You can also setup specific logging by doing the following

```
auth.* @192.168.253.86:514 # only for authentication based records
```

Results

This is what your folder will look like with the host name of the server or device

```
drwx----- 2 root root 42 Aug 29 22:30 RT-AC5300-RANGE-25D1EC7-C
drwx----- 2 root root 82 Aug 29 22:32 SFL-LIN-000
drwx----- 2 root root 87 Aug 29 22:32 sfl-web-004
```

This is a look within a folder of a server

```
[/var/log]# cd SFL-LIN-000/

root@SFL-LIN-000.ONLING.COM : Linux : Thu Aug 29 22:35:01 :
[/var/log/SFL-LIN-000]# ls -lrt
total 16
-rw----- 1 root root 850 Aug 29 22:30 rsyslogd.log
-rw----- 1 root root 56 Aug 29 22:32 sssd_kcm.log
-rw----- 1 root root 948 Aug 29 22:32 systemd.log
-rw----- 1 root root 251 Aug 29 22:32 CROND.log
```

Linux - Bag of Tricks

Introduction

This document has many useful command.

Linux Set Time Examples

You can also simplify format using following syntax:

```
date +%Y%m%d -s "20081128"
```

To set time use the following syntax:

```
date +%T -s "10:13:13"
```

Use the following syntax to set new data and time:

```
date --set="STRING"
```

For example, set new data to 2 Oct 2006 18:00:00, type the following command as root user:

```
date -s "2 OCT 2006 18:00:00"
```

OR

```
date --set="2 OCT 2006 18:00:00"
```

Rsync Copy Examples

This is to move files from one server to another

Ending the folder WITHOUT a "/" slash means copy that folder everything in that folder

Ending the folder WITH a "/" slash means copy everything within that folder

Example for "remote to local" location

```
rsync -chavzP --stats --progress -e ssh user@remote_host:/remote_folder/dir1/ /local_folder/dir1/
```

Example for "local to remote" location

```
rsync -chavzP --stats --progress -e ssh /local_folder/dir1/ user@remote_host:/remote_folder/dir1/
```

Rsync Auto Login while sending

Example to add a Rsync key on the remote server

On the local server simply login as a given user ex: ROOT or USER

```
ssh-keygen -t rsa
```

If it already exists simply hit "n"

```
Generating public/private rsa key pair.  
Enter file in which to save the key (/root/.ssh/id_rsa):  
/root/.ssh/id_rsa already exists.  
Overwrite (y/n)?
```

If not then simply hit enter through all options

Example: of using ROOT

```

Generating public/private rsa key pair.
Enter file in which to save the key (/root/.ssh/id_rsa):
Enter passphrase (empty for no passphrase):
Enter same passphrase again:
Your identification has been saved in /root/.ssh/id_rsa
Your public key has been saved in /root/.ssh/id_rsa.pub
The key fingerprint is:
SHA256:JoMN/cxvsqZWBHws4eyrU5Q0F0qRe//44qdrriQmbU root@DSS-US-TMAP-XXX
The key's randomart image is:
+---[RSA 3072]----+
|  .+=..      |
|  =B.+       |
|  ..=O       |
|  ==+o       |
|  = E=...    |
|  o... oo    |
|  ..o..++ o  |
|  .oo+o==*.  |
+----[SHA256]-----+
You have mail in /var/spool/mail/root

```

Run the following to add the key to the remote server, you can also use IP instead of host name

```
ssh-copy-id -i ~/.ssh/id_rsa.pub remuser@sfl-lin-001
```

Example of using a USER you will have to enter yes and the USER password

```

/usr/bin/ssh-copy-id: INFO: Source of key(s) to be installed: "/root/.ssh/id_rsa.pub"
The authenticity of host 'sfl-lin-020 (192.168.136.80)' can't be established.
ED25519 key fingerprint is SHA256:oZnvrgY+2Xpd2/huaffvzLMBAgI52AMPUmq/LPLIXbE.
This key is not known by any other names
Are you sure you want to continue connecting (yes/no/[fingerprint])? yes
/usr/bin/ssh-copy-id: INFO: attempting to log in with the new key(s), to filter out any that are already installed
/usr/bin/ssh-copy-id: INFO: 1 key(s) remain to be installed -- if you are prompted now it is to install the new keys
remuser@dss-us-map-020's password:
tput: No value for $TERM and no -T specified
tput: No value for $TERM and no -T specified
tput: No value for $TERM and no -T specified
tput: No value for $TERM and no -T specified
tput: No value for $TERM and no -T specified
tput: No value for $TERM and no -T specified
tput: No value for $TERM and no -T specified
Number of key(s) added: 1
Now try logging into the machine, with: "ssh 'remuser@sfl-lin-020'"
and check to make sure that only the key(s) you wanted were added.

```

Optional: If the command cannot be run above you can copy the key to the remote server manually into the “authorized_keys” file

```

cd
cd .ssh
vi authorized_keys

```

Optional: Change the permissions on the local server

```
chmod 600 ~/.ssh/*  
chmod 711 ~/.ssh  
chmod 711 ~
```

Synology Rsync

```
rsync -aXHmS --syno-acl /volum1/[xxx] /volume2/[xxx]
```

-a, --archive archive mode; equals -rlptgoD (no -H,-A,-X)
-p, --perms preserve permissions
-X, --xattrs preserve extended attributes
-o, --owner preserve owner (super-user only)
-g, --group preserve group
--syno-acl copy Synology ACL data

I use the following options myself:

```
rsync -avhxWog --stats --backup --suffix $OLDSUFFIX --exclude-from=$RSYEXCL --syno-pseudo-root
```

No idea why I list options "og" since they're implied by -a, but it works...

Regards, Arild

PS: "rsync --help" lists all available options for rsync

Find and Replace String with `sed`

There are several versions of `sed`, with some functional differences between them. macOS uses the BSD version, while most Linux distributions come with GNU `sed` pre-installed by default. We'll use the GNU version.

The general form of searching and replacing text using `sed` takes the following form:

```
sed -i 's/SEARCH_REGEX/REPLACEMENT/g' INPUTFILE
```

Cop

- `-i` - By default, `sed` writes its output to the standard output. This option tells `sed` to edit files in place. If an extension is supplied (ex -i.bak), a backup of the original file is created.

- `s` - The substitute command, probably the most used command in sed.
- `///` - Delimiter character. It can be any character but usually the slash (`/`) character is used.
- `SEARCH_REGEX` - Normal string or a regular expression to search for.
- `REPLACEMENT` - The replacement string.
- `g` - Global replacement flag. By default, `sed` reads the file line by line and changes only the first occurrence of the `SEARCH_REGEX` on a line. When the replacement flag is provided, all occurrences are replaced.
- `INPUTFILE` - The name of the file on which you want to run the command.

Find and Replace String with `sed` within `vi`

This is to search and replace a file globally withing vi

```
:%s/search_string/replacement_string/g
```

Kill Users in Linux

This is to be used when trying to kill users using the connection, replace the `?` with the number of the session.

```
pkill -KILL -t pts/?
```

Create a CERT

First, you need to generate the private key and the Certificate Signing Request (CSR). You can do this via the `openssl` command:

```
openssl req -nodes -newkey rsa:2048 -keyout privatekey.key -out mail.csr
```

Then, generate a signing request

```
openssl x509 -req -days 365 -in mail.csr -signkey privatekey.key -out secure.crt
```

Create a localhost cert on the server

```
openssl req -newkey rsa:2048 -nodes -keyout /etc/pki/tls/private/localhost.key -x509 -days 365 -out  
/etc/pki/tls/certs/localhost.crt
```

Mariadb Log Rotate

If log file is large, try if the logrotate

```
logrotate --force /etc/logrotate.d/mariadb
```

MySQL Fail to Start

If MySQL does not restart, it probably will not as the index of the log files will not be changed

```
:d /var/lib/mysql  
mv ib_logfile0 ib_logfile0.old  
mv ib_logfile1 ib_logfile1.old  
systemctl restart mariadb
```

Configure Rsync

Useful for system migrations

Create a “/etc/rsyncd.conf” containing:

```
[root]  
exclude = /dev /etc/fstab /proc /sys  
path = /  
read only = yes  
list = yes  
uid = root  
gid = root
```

Enable and start:

```
systemctl enable rsyncd.service  
systemctl start rsyncd.service
```

Change Run level

```
systemctl set-default multi-user.target
```

To switch from graphical to multi-user:

```
systemctl isolate multi-user.target;
```

Change Local settings

```
# timedatectl set-timezone Europe/London
```

```
# localectl set-locale LANG=en_GB.UTF-8
```

```
# localectl set-keymap uk
```

Temporary change

```
$ loadkeys us
```

Configure Alternate Authentication

```
authconfig-tui
```

SSD Considerations

Change the value of “`issue_discards`” option from 0 to 1 in “`/etc/lvm/lvm.conf`”

```
#  
systemctl enable fstrim.timer
```

Adjust “`/etc/fstab`”

```
/dev/mapper/xxx /XXX    xfs    defaults,noatime,discard    0 0
```

Optionally set `/tmp` in RAM

```
# systemctl enable tmp.mount
```

Adding a Disk

```
# parted /dev/sdx
```

```
mklabel gpt
```

```
unit s
```

```
mkpart primary 2048s 100%
```

```
set 1 lvm on
```

```
quit
```

```
# pvcreate /dev/sdx1
# vgcreate rl_ssd /dev/sdx1
# lvcreate -L 50GB -n mysql rl_ssd
# mkfs.xfs /dev/rl-ssd/mysql
# blkid /dev/sdc

# chown mysql:mysql /var/lib/mysql
```

Growing a lvm partition

```
# parted /dev/sdc
```

```
(parted) unit b
```

```
(parted) print free
```

Number	Start	End	Size	Type	File system	Flags
1	31744B	5368709119B	5368677376B	primary		
	5368709120B	21474836479B	16106127360B			Free Space

```
(parted) resizepart 1 21474836479B
```

```
(parted) quit
```

```
# pvresize /dev/sdc1
```

Updating Bootloader configuration

```
/etc/default/grub
```

```
grub2-mkconfig -o /boot/grub2/grub.cfg
```

NMAP Scan for all Open Ports

TCP

```
sudo nmap -sT -p- onling.com
```

UDP

```
sudo nmap -sU -p- onling.com
```

Linux - How to Decrease an LVM Partition

Note: In this example we are working in CentOS 7, some commands may differ in different Linux distributions. As of CentOS 7 the default file system is XFS which is not currently possible to shrink, this example is working with the ext4 file system.

In this example we will work through shrinking logical volume `/var/centos/var` from 10GB to 5GB.

Overview of Logical Volume Manager (LVM)

Before working through the resizing process it's important you first understand some basic concepts around physical volumes, volume groups, logical volumes, and the file system.

- **Physical Volume (PV):** This can be created on a whole physical disk (think `/dev/sda`) or a Linux partition.
- **Volume Group (VG):** This is made up of at least one or more physical volumes.
- **Logical Volume (LV):** This is sometimes referred to as the partition, it sits within a volume group and has a file system written to it.
- **File System:** A file system such as ext4 will be on the logical volume.

LVM Resize – How to decrease or shrink the logical volume

To decrease the size of an LVM partition you must first decrease the file system within in order to avoid possible data corruption. As there is the potential for this to happen if you enter the command incorrectly, it is strongly recommended that you have a full backup of your data before proceeding. Shrinking a logical volume will give you more space in the volume group, meaning that you could instead [extend another logical volume](#) with this new found space.

The first step will depend on if you're looking to shrink a LVM root volume, or non-root volume.

Shrinking a root volume

The root volume would typically be the logical volume that is mounted to /. You cannot unmount this to shrink it as it's in use by the running operating system meaning that you will have to first boot from a Live CD to complete this. Once booted into the Live CD, you may first need to run the below command to pick up LVM volumes, however this usually happens during boot so may not be required, if in doubt just run it.

```
vgchange -a y
```

Shrinking a non-root volume

Alternatively if the volume you are shrinking is a non-root volume, that is any other volume not mounted to the root of the file system, you can unmount the volume as shown below to proceed. Please note that when you unmount the volume the data will not be available, so you may need to schedule down time and stop running applications that use data from it prior to unmounting. Unmount by specifying either the logical volume or the location it's currently mounted to, in the below example we specify the logical volume which can be found in /dev/(vg-name)/(lv-name).

```
umount /dev/centos/var
```

All following steps now apply to both a root or non-root volume.

Before being able to attempt to shrink the size of an LVM volume, you must first run a file system check on it. If you don't do this, you will get an error message and will not be able to proceed. This is a required step as resizing a file system in a bad state could cause data corruption. The -f flag makes the check run even if the file system appears clean, while -y assumes yes to all questions and will respond if asked to fix a problem.

```
e2fsck -fy /dev/centos/var
```

Next you need to shrink the file system, to be safe we're going to shrink the file system lower than what the logical volume will shrink to. This is because we don't want to accidentally shrink the logical volume to a size lower than the file system in the next step, as this can result in corruption and data loss. Don't worry, we'll reclaim the space at the end.

The command below will shrink the file system so that it is only 4G in size total, note that whatever size you specify to shrink to you must have in free space within the file system otherwise you must first delete data.

```
resize2fs /dev/centos/var 4G
```

Once the file system has been reduced, we can shrink the size of the logical volume with the `lvreduce` command. Reduce this to the size that you want the volume to be, as specified by the `-L` flag. Instead if you want to reduce by a specified size, simply put a `-` in front of the size. Both are shown below for completeness, however you only need to run one.

To reduce to 5G

```
lvreduce -L 5G /dev/vg/disk-name
```

To reduce by 5G

```
lvreduce -L -5G /dev/vg/disk-name
```

Once you execute the `lvreduce` command you will get a warning advising the size you have chosen to reduce to so use this as a chance to confirm you're shrinking the logical volume to a size that is NOT smaller than the size you previously shrunk the file system to. Once you have confirmed it's fine to proceed enter `'y'` and press enter.

After the logical volume has been lowered to the required size, run `resize2fs` on the volume as this will extend the file system to use all available space within the logical volume. This makes use of all remaining free space so that none is wasted from when we previously shrunk the file system to a lower size than the logical volume.

```
resize2fs /dev/centos/var
```

At this point all that's left to do is mount the volume. If this was a root volume and you're working within a Live CD, simply boot back into your primary Linux operating system.

If this was a non-root volume and you unmounted it to complete the reduction, simply mount it back. You can do this with `'mount -a'` assuming you have the configuration already set in `/etc/fstab`, otherwise specify the logical volume and where it should mount to. Here we're manually mounting to `/mnt` just for testing.

```
mount /dev/centos/var /mnt
```

After you've either booted back to primary operating system or completed the mount, check the space shown with the `'df'` command to confirm it has been decreased as expected.

```
[root@CentOS7 /]# df -h
Filesystem      Size  Used Avail Use% Mounted on
/dev/mapper/centos-root 9.8G  1.4G  8.5G  14% /
devtmpfs        908M   0  908M   0% /dev
```



```
tmpfs          914M    0 914M   0% /dev/shm
tmpfs          914M  8.6M 905M   1% /run
tmpfs          914M    0 914M   0% /sys/fs/cgroup
/dev/sda1      497M  96M 402M  20% /boot
/dev/mapper/centos-var 4.8G  20M 4.6G   1% /mnt
```

In this example `/dev/centos/var` is correctly showing as shrunk down from the original 10G.

Linux - Increase the size of a LVM Partition

This will cover how to increase the disk space for a VMware virtual machine running Linux that is using logical volume manager (LVM). Firstly we will be increasing the size of the actual disk on the VMware virtual machine, so at the hardware level – this is the VM's .vmdk file. Once this is complete we will get into the virtual machine and make the necessary changes through the operating system in order to take advantage of the additional space that has been provided by the hard drive being extended. This will involve creating a new partition with the new space, expanding the volume group and logical group, then finally resizing the file system.

Important Note: Be very careful when working with the commands in this article as they have the potential to cause a lot of damage to your data. If you are working with virtual machines make sure you take a snapshot of your virtual machine beforehand, or otherwise have some other form of up to date backup before proceeding. Note that a snapshot must not be taken until after the virtual disk has been increased, otherwise you will not be able to increase it. It could also be worth cloning the virtual machine first and testing out this method on the clone.

Prerequisites: As this method uses the additional space to create a primary partition, you must not already have 4 partitions as you will not be able to create more than 4. If you do not have space for another partition then you will need to consider a different method, there are some others in the above list.

Throughout examples we will be working with a VMware virtual machine running Debian 6, this was set up with a 20gb disk and we will be increasing it by 10gb for a total final size of 30gb.

Identifying the partition type

As this method focuses on working with LVM, we will first confirm that our partition type is actually Linux LVM by running the below command.

```
fdisk -l
```

```
Disk /dev/sda: 100 GiB, 107374182400 bytes, 209715200 sectors
Units: sectors of 1 * 512 = 512 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes
Disklabel type: gpt
Disk identifier: AFF16F8B-94D1-4D49-98B2-C99EAE573683

Device      Start      End      Sectors  Size Type
/dev/sda1    2048    1230847    1228800   600M EFI System
/dev/sda2  1230848    3327999    2097152    1G Linux filesystem
/dev/sda3  3328000 209713151 206385152 98.4G Linux LVM

Disk /dev/mapper/rl-root: 94.5 GiB, 101418270720 bytes, 198082560 sectors
Units: sectors of 1 * 512 = 512 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes

Disk /dev/mapper/rl-swap: 4 GiB, 4248829952 bytes, 8298496 sectors
Units: sectors of 1 * 512 = 512 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes
```

As you can see in the above image /dev/sda3 is listed as “Linux LVM” and it has the ID of 8e. The 8e hex code shows that it is a Linux LVM, while 83 shows a Linux native partition. Now that we have confirmed we are working with an LVM we can continue. For increasing the size of a Linux native partition (hex code 83).

Below is the disk information showing that our initial setup only has the one 95gb disk currently, which is under the logical volume named /dev/mapper/rl-root – this is what we will be expanding with the new disk.


```
Filesystem      Size  Used Avail Use% Mounted on
devtmpfs        1.9G     0  1.9G   0% /dev
tmpfs           1.9G     0  1.9G   0% /dev/shm
tmpfs           1.9G  198M  1.7G  11% /run
tmpfs           1.9G     0  1.9G   0% /sys/fs/cgroup
/dev/mapper/rl-root 95G   84G   12G  88% /
/dev/sda2       1014M  293M  722M  29% /boot
/dev/sda1        599M   5.8M  594M   1% /boot/efi
tmpfs           374M     0  374M   0% /run/user/1000
```

Note: that /dev/mapper/rl-root is the volume made up from /dev/sda3 currently – this is what we will be expanding.

Increasing the virtual hard disk

First off we increase the allocated disk space on the virtual machine itself. This is done by right clicking the virtual machine in vSphere, selecting edit settings, and then selecting the hard disk. In the below image I have changed the previously set hard disk of 100gb to 350gb while the virtual machine is up and running. Once complete click OK, this is all that needs to be done in VMware for

this process.



If you are not able to modify the size of the disk, the provisioned size setting is greyed out. This can happen if the virtual machine has a snapshot in place, these will need to be removed prior to making the changes to the disk. Alternatively you may need to shut down the virtual machine if it does not allow you to add or increase disks on the fly, if this is the case make the change then power it back on.

Detect the new disk space

Once the physical disk has been increased at the hardware level, we need to get into the operating system and create a new partition that makes use of this space to proceed.

Before we can do this we need to check that the new unallocated disk space is detected by the server, you can use “fdisk -l” to list the primary disk. You will most likely see that the disk space is still showing as the same original size, at this point you can either reboot the server and it will detect the changes on boot or you can rescan your devices to avoid rebooting by running the below command. Note you may need to change host0 depending on your setup.

```
echo "- - -" > /sys/class/scsi_host/host0/scan
```

Below is an image after performing this and confirming that the new space is displaying.

```
Disk /dev/sda: 100 GiB, 107374182400 bytes, 209715200 sectors
Units: sectors of 1 * 512 = 512 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes
Disklabel type: gpt
Disk identifier: AFF16F8B-94D1-4D49-9BB2-C99EAE573683

Device      Start      End      Sectors  Size Type
/dev/sda1    2048      1230847  1228800  600M EFI System
/dev/sda2   1230848   3327999  2097152  1G Linux filesystem
/dev/sda3   3328000  209713151 206385152 98.4G Linux LVM
```

Partition the new disk space

As outlined in my previous images the disk in my example that I am working with is `/dev/sda`, so we use `fdisk` to create a new primary partition to make use of the new expanded disk space. Note that we do not have 4 primary partitions already in place, making this method possible.

```
fdisk /dev/sda
```

We are now using `fdisk` to create a new partition, the inputs I have entered in are shown below in bold. Note that you can press 'm' to get a full listing of the `fdisk` commands.

'n' was selected for adding a new partition.

Welcome to fdisk (util-linux 2.32.1).

Changes will remain in memory only, until you decide to write them.

Be careful before using the write command.

GPT PMBR size mismatch (209715199 != 734003199) will be corrected by write.

The backup GPT table is not on the end of the device. This problem will be corrected by write.

Command (m for help):

As I already have `/dev/sda1`, `sda2` and `sda3` as shown in previous images, I have gone with using '4' for this new partition which will be created as `/dev/sda4`

Enter the "n" for new partition and enter for the rest of the defaults

Command (m for help): n

Partition number (4-128, default 4):

First sector (209713152-734003166, default 209713152):

Last sector, +sectors or +size{K,M,G,T,P} (209713152-734003166, default 734003166):

Created a new partition 4 of type 'Linux filesystem' and of size 250 GiB.

Command (m for help):

'p' to view the current changes in the session

Command (m for help): p

Disk /dev/sda: 350 GiB, 375809638400 bytes, 734003200 sectors

Units: sectors of 1 * 512 = 512 bytes

```
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes
Disklabel type: gpt
Disk identifier: AFF16F8B-94D1-4D49-9BB2-C99EAE573683
```

Device	Start	End	Sectors	Size	Type
/dev/sda1	2048	1230847	1228800	600M	EFI System
/dev/sda2	1230848	3327999	2097152	1G	Linux filesystem
/dev/sda3	3328000	209713151	206385152	98.4G	Linux LVM
/dev/sda4	209713152	734003166	524290015	250G	Linux filesystem

```
Command (m for help):
```

As you can see the new partition of 150gb is a 8e meaning a Linux file system which is correct, older version we needed to change this.

'w' is used to write the table to disk and exit, basically all the changes that have been done will be saved and then you will be exited from fdisk.

```
Command (m for help): w
The partition table has been altered.
Syncing disks.
```

You will see a warning which basically means in order to use the new table with the changes a system reboot is required. If you can not see the new partition using "fdisk -l" you may be able to run "partprobe -s" to rescan the partitions. In my test I did not require either of those things at this stage (I do a reboot later on), straight after pressing 'w' in fdisk I was able to see the new /dev/sda3 partition of my 10gb of space as displayed in the below image.

That's all for partitioning, we now have a new partition which is making use of the previously unallocated disk space from the increase in VMware.

Increasing the logical volume

We use the pvcreate command which creates a physical volume for later use by the logical volume manager (LVM). In this case the physical volume will be our new /dev/sda4 partition.

```
pvcreate /dev/sda4
Physical volume "/dev/sda4" successfully created.
```

Next we need to confirm the name of the current volume group using the `vgdisplay` command. The name will vary depending on your setup, for me it is the name of my test server. `vgdisplay` provides lots of information on the volume group, I have only shown the name and the current size of it for this example.

```
vgdisplay
--- Volume group ---
VG Name          rl
System ID
Format           lvm2
Metadata Areas   1
Metadata Sequence No 3
VG Access        read/write
VG Status        resizable
MAX LV           0
Cur LV          2
Open LV          2
Max PV           0
Cur PV          1
Act PV           1
VG Size          98.41 GiB
PE Size          4.00 MiB
Total PE         25193
Alloc PE / Size  25193 / 98.41 GiB
Free PE / Size   0 / 0
VG UUID          16Qr51-iLg8-HDNB-MkUc-TB5c-dL9j-rnpHUE
```

Now we extend the 'rl' volume group by adding in the physical volume of `/dev/sda4` which we created using the `pvcreate` command earlier.

```
vgextend rl /dev/sda4
Volume group "rl" successfully extended
```

Using the `pvscan` command we scan all disks for physical volumes, this should confirm the original `/dev/sda5` partition and the newly created physical volume `/dev/sda4`

```
pvscan
PV /dev/sda3  VG rl          lvm2 [98.41 GiB / 0   free]
PV /dev/sda4  VG rl          lvm2 [<250.00 GiB / <250.00 GiB free]
Total: 2 [<348.41 GiB] / in use: 2 [<348.41 GiB] / in no VG: 0 [0   ]
```

Next we need to increase the logical volume (rather than the physical volume) which basically means we will be taking our original logical volume and extending it over our new partition/physical volume of `/dev/sda4`.

Firstly confirm the path of the logical volume using `lvdisplay`. This path name will vary depending on your setup.

```
lvdisplay
```

```
--- Logical volume ---
```

```
LV Path          /dev/rl/root
```

```
LV Name          root
```

```
VG Name          rl
```

```
LV UUID          mb2gT4-2oqM-8icq-B8S6-A3lZ-9lvi-scDZqS
```

```
LV Write Access   read/write
```

```
LV Creation host, time mfb-us-lin-001, 2022-10-08 19:34:32 -0400
```

```
LV Status         available
```

```
# open           1
```

```
LV Size          94.45 GiB
```

```
Current LE       24180
```

```
Segments         1
```

```
Allocation       inherit
```

```
Read ahead sectors    auto
```

```
- currently set to    8192
```

```
Block device       253:0
```

```
--- Logical volume ---
```

```
LV Path          /dev/rl/swap
```

```
LV Name          swap
```

```
VG Name          rl
```

```
LV UUID          NWNCL3-rzD7-av3v-IRP0-OQy9-4CcE-phna9T
```

```
LV Write Access   read/write
```

```
LV Creation host, time mfb-us-lin-001, 2022-10-08 19:34:33 -0400
```

```
LV Status         available
```

```
# open           2
```

```
LV Size          <3.96 GiB
```

```
Current LE       1013
```

```
Segments         1
```

```
Allocation       inherit
```

```
Read ahead sectors    auto
```

```
- currently set to    8192
```

```
Block device       253:1
```


The logical volume is then extended using the lvextend command.

```
lvextend /dev/rl/root /dev/sda4
```

Size of logical volume rl/root changed from 94.45 GiB (24180 extents) to <344.45 GiB (88179 extents).

Logical volume rl/root successfully resized

There is then one final step which is to resize the file system so that it can take advantage of this additional space, this is done using the xfs_growfs command. Note that this may take some time to complete, it took about 30 seconds for my additional space.

```
xfs_growfs /dev/rl/root
```

```
meta-data=/dev/mapper/rl-root  isize=512  agcount=4, agsize=6190080 blks
```

```
          =                sectsz=512  attr=2, projid32bit=1
```

```
          =                crc=1      finobt=1, sparse=1, rmapbt=0
```

```
          =                reflink=1  bigtime=0 inobtcount=0
```

```
data      =                bsize=4096  blocks=24760320, imaxpct=25
```

```
          =                sunit=0    swidth=0 blks
```

```
naming    =version 2        bsize=4096  ascii-ci=0, ftype=1
```

```
log        =internal log    bsize=4096  blocks=12090, version=2
```

```
          =                sectsz=512  sunit=0 blks, lazy-count=1
```

```
realtime  =none            extsz=4096  blocks=0, rtextents=0
```

```
data blocks changed from 24760320 to 90295296
```

That's it, now with the 'df' command we can see that the total available disk space has been increased.

```
df -h
```

Filesystem	Size	Used	Avail	Use%	Mounted on
devtmpfs	1.8G	0	1.8G	0%	/dev
tmpfs	1.8G	0	1.8G	0%	/dev/shm
tmpfs	1.8G	8.7M	1.8G	1%	/run
tmpfs	1.8G	0	1.8G	0%	/sys/fs/cgroup
/dev/mapper/rl-root	345G	85G	260G	25%	/
/dev/sda2	1014M	319M	696M	32%	/boot
/dev/sda1	599M	5.8M	594M	1%	/boot/efi
tmpfs	367M	0	367M	0%	/run/user/0

260gb more drive space, aaaaaaah ☺☺

Linux - Setting up an SSL secured Webserver with CentOS

This guide will explain how to set up a site over https. The tutorial uses a self signed key so will work well for a personal website or testing purposes. This is provided as is so proceed at your own risk and take backups!

1. Getting the required software

For an SSL encrypted web server you will need a few things. Depending on your install you may or may not have OpenSSL and mod_ssl, Apache's interface to OpenSSL. Use yum to get them if you need them.

```
yum install mod_ssl openssl
```

Yum will either tell you they are installed or will install them for you.

2. Generate a self-signed certificate

Using OpenSSL we will generate a self-signed certificate. If you are using this on a production server you are probably likely to want a key from a Trusted Certificate Authority, but if you are just using this on a personal site or for testing purposes a self-signed certificate is fine. To create the key you will need to be root so you can either su to root or use sudo in front of the commands

```
# Generate private key
openssl genrsa -out ca.key 2048

# Generate CSR
```

```
openssl req -new -key ca.key -out ca.csr

# Generate Self Signed Key
openssl x509 -req -days 365 -in ca.csr -signkey ca.key -out ca.crt

# Copy the files to the correct locations
cp ca.crt /etc/pki/tls/certs
cp ca.key /etc/pki/tls/private/ca.key
cp ca.csr /etc/pki/tls/private/ca.csr
```

WARNING: Make sure that you **copy** the files and do not **move** them if you use SELinux. Apache will complain about missing certificate files otherwise, as it cannot read them because the certificate files do not have the right SELinux context.

If you have moved the files and not copied them, you can use the following command to correct the SELinux contexts on those files, as the correct context definitions for `/etc/pki/*` come with the bundled SELinux policy.

```
restorecon -RvF /etc/pki
```

Then we need to update the Apache SSL configuration file

```
vi +/SSLCertificateFile /etc/httpd/conf.d/ssl.conf
```

Change the paths to match where the Key file is stored. If you've used the method above it will be

```
SSLCertificateFile /etc/pki/tls/certs/ca.crt
```

Then set the correct path for the Certificate Key File a few lines below. If you've followed the instructions above it is:

```
SSLCertificateKeyFile /etc/pki/tls/private/ca.key
```

Quit and save the file and then restart Apache

```
/etc/init.d/httpd restart
```

All being well you should now be able to connect over https to your server and see a default Centos page. As the certificate is self signed browsers will generally ask you whether you want to accept the certificate.

3. Setting up the virtual hosts

Just as you set [VirtualHosts](#) for http on port 80 so you do for https on port 443. A typical [VirtualHost](#) for a site on port 80 looks like this

```
<VirtualHost *:80>
    <Directory /var/www/vhosts/yoursite.com/httpdocs>
        AllowOverride All
    </Directory>
    DocumentRoot /var/www/vhosts/yoursite.com/httpdocs
    ServerName yoursite.com
</VirtualHost>
```

To add a sister site on port 443 you need to add the following at the top of your file

```
NameVirtualHost *:443
```

and then a [VirtualHost](#) record something like this:

```
<VirtualHost *:443>
    SSLEngine on
    SSLCertificateFile /etc/pki/tls/certs/ca.crt
    SSLCertificateKeyFile /etc/pki/tls/private/ca.key
    <Directory /var/www/vhosts/yoursite.com/httpsdocs>
        AllowOverride All
    </Directory>
    DocumentRoot /var/www/vhosts/yoursite.com/httpsdocs
    ServerName yoursite.com
</VirtualHost>
```

Restart Apache again using

```
/etc/init.d/httpd restart
```

4. Configuring the firewall

You should now have a site working over https using a self-signed certificate. If you can't connect you may need to open the port on your firewall. To do this amend your iptables rules:

```
iptables -A INPUT -p tcp --dport 443 -j ACCEPT  
/sbin/service iptables save  
iptables -L -v
```

Linux - Samba Setup Rocky

9

Step 1: Install Samba on Linux

To get started out with **Samba**, install the **Samba** core packages including the client package:

```
dnf install -y samba samba-common samba-client
```

Install-Samba in Linux

```
[tecmint@rocky-8 ~]$  
[tecmint@rocky-8 ~]$ sudo dnf install samba samba-common samba-client  
Last metadata expiration check: 0:27:23 ago on Sat 11 Dec 2021 11:51:53 PM EAT.  
Package samba-common-4.13.3-5.el8_4.noarch is already installed.  
Dependencies resolved.  
=====
```

Package	Architecture	Version	Repository	Size
Installing:				
samba	x86_64	4.14.5-2.el8	baseos	846 k
samba-client	x86_64	4.14.5-2.el8	baseos	700 k
Upgrading:				
libsmbclient	x86_64	4.14.5-2.el8	baseos	146 k
libwbclient	x86_64	4.14.5-2.el8	baseos	120 k
samba-client-libs	x86_64	4.14.5-2.el8	baseos	5.4 M
samba-common	noarch	4.14.5-2.el8	baseos	219 k

The command installs the packages specified along with the dependencies as displayed on the output. After the installation is complete, you will get a summary of all the packages that have been installed.

Samba Installation Completes

```
Verifying      : samba-common-4.14.5-2.el8.noarch      11/14
Verifying      : samba-common-4.13.3-5.el8_4.noarch   12/14
Verifying      : samba-common-libs-4.14.5-2.el8.x86_64 13/14
Verifying      : samba-common-libs-4.13.3-5.el8_4.x86_64 14/14
Installed products updated.

Upgraded:
  libsmbclient-4.14.5-2.el8.x86_64      libwbclient-4.14.5-2.el8.x86_64
  samba-client-libs-4.14.5-2.el8.x86_64  samba-common-4.14.5-2.el8.noarch
  samba-common-libs-4.14.5-2.el8.x86_64

Installed:
  samba-4.14.5-2.el8.x86_64      samba-client-4.14.5-2.el8.x86_64
  samba-common-tools-4.14.5-2.el8.x86_64  samba-libs-4.14.5-2.el8.x86_64

Complete!
[tecmint@rocky-8 ~]$
```

Step 2: Create and Configure Samba Shares

Once all the **samba** packages have been installed, the next step is to configure the **samba shares**. A samba share is simply a directory that is going to be shared across client systems in the network.

Here, we are going to create a samba share called **/data** in the **/srv/tecmint/** directory path.

```
mkdir -p /srv/tecmint/data
```

Next, we will assign permissions and ownership as follows.

```
chmod -R 755 /srv/tecmint/data
chown -R nobody:nobody /srv/tecmint/data
chcon -t samba_share_t /srv/tecmint/data
```

Create Samba Share Directory

```
[tecmint@rocky-8 ~]$ sudo mkdir -p /srv/tecmint/data
[tecmint@rocky-8 ~]$
[tecmint@rocky-8 ~]$
[tecmint@rocky-8 ~]$ sudo chmod -R 755 /srv/tecmint/data
[tecmint@rocky-8 ~]$
[tecmint@rocky-8 ~]$ sudo chown -R nobody:nobody /srv/tecmint/data
[tecmint@rocky-8 ~]$
[tecmint@rocky-8 ~]$ sudo chcon -t samba_share_t /srv/tecmint/data
[tecmint@rocky-8 ~]$
```

Next, we are going to make some configurations in the **smb.conf** configuration file which is Samba's main configuration file. But before we do so, we will back up the file by renaming it with a different file extension.

```
mv /etc/samba/smb.conf /etc/samba/smb.conf.bak
```

Next, we are going to create a new configuration file.

```
vim /etc/samba/smb.conf
```

We will define policies on who can access the samba share by adding the lines shown in the configuration file.

```
[global]
workgroup = WORKGROUP
server string = Samba Server %v
netbios name = rocky-8
security = user
map to guest = bad user
dns proxy = no
ntlm auth = true


[Public]
path = /srv/tecmint/data
browsable = yes
writable = yes
guest ok = yes
read only = no
```

Save and exit the configuration file.

To verify the configurations made, run the command:

```
testparm
```

Verify Samba Configuration


```
[tecmint@rocky-8 ~]$  
[tecmint@rocky-8 ~]$ sudo testparm   
Load smb config files from /etc/samba/smb.conf  
Loaded services file OK.  
Weak crypto is allowed  
  
Server role: ROLE_STANDALONE  
  
Press enter to see a dump of your service definitions  
  
# Global parameters  
[global]  
    dns proxy = No  
    map to guest = Bad User  
    security = USER  
    server string = Samba Server %v  
    idmap config * : backend = tdb  
  
[Public]  
    guest ok = Yes  
    path = /srv/tecmint/data  
    read only = No
```

Next, start and enable Samba daemons as shown.

```
systemctl enable --now smb;systemctl enable --now nmb
```

Be sure to confirm that both the **smb** and **nmb** daemons are running.

```
systemctl status smb;systemctl status nmb
```

Verify Samba Status

```
[tecmint@rocky-8 ~]$ sudo systemctl status smb ←
● smb.service - Samba SMB Daemon
   Loaded: loaded (/usr/lib/systemd/system/smb.service; enabled; vendor preset: d
   Active: active (running) since Sun 2021-12-12 00:58:43 EAT; 11min ago
     Docs: man:smbd(8)
           man:samba(7)
           man:smb.conf(5)
  Main PID: 8007 (smbd)
    Status: "smbd: ready to serve connections..."
     Tasks: 4 (limit: 11090)

[tecmint@rocky-8 ~]$ sudo systemctl status nmb ←
● nmb.service - Samba NMB Daemon
   Loaded: loaded (/usr/lib/systemd/system/nmb.service; enabled; vendor preset: di
   Active: active (running) since Sun 2021-12-12 00:59:00 EAT; 11min ago
     Docs: man:nmbd(8)
           man:samba(7)
           man:smb.conf(5)
  Main PID: 8105 (nmbd)
    Status: "nmbd: ready to serve connections..."
     Tasks: 1 (limit: 11090)
  Memory: 2.8M
```

To enable access to samba share from remote Windows systems, you need to open the samba protocol on the firewall.

```
firewall-cmd --permanent --add-service=samba
firewall-cmd --reload
firewall-cmd --list-services
```


Step 3: Accessing Samba Share from Windows

Thus far, we have installed **samba** and configured our **samba share**. We are now ready to access it remotely. To do this on a Windows client, press the Windows logo key + R to launch the **Run** dialog.

In the textfield provided, enter the samba server's IP address as shown:


```
\\server-ip
```

Access Samba Share from Windows



The following window labeled '**Public**' will pop up. Remember, this is the directory that points to our samba share in the **/srv/tecmint/data** directory.

Access Samba Share Directory on Windows




Currently, our directory is empty as we have not created any files. So, we will head back to our terminal and create a few files in the samba share directory.

```
cd /srv/tecmint/data  
touch file{1..3}.txt
```

Now, we will navigate to the '**Public**' folder where the files we created earlier will be displayed.

Access Samba Share Files on Windows



Perfect. We have successfully managed to access our **samba share**. However, our directory is accessible to anyone and everybody can edit and delete files at will, which is not recommended especially if you plan to host sensitive files.

In the next step, we will demonstrate how you can create and configure a secure samba share directory.

Step 4: Secure Samba Share Directory

First, we will create a new samba user.

```
useradd smbuser
```

Next, we will configure a password for the samba user. This is the password that will be used during authentication.

```
smbpasswd -a smbuser
```

Create Samba User

```
[tecmint@rocky-8 ~]$ sudo useradd smbuser  
[tecmint@rocky-8 ~]$  
[tecmint@rocky-8 ~]$  
[tecmint@rocky-8 ~]$ sudo smbpasswd -a smbuser  
New SMB password:  
Retype new SMB password:  
Added user smbuser.  
[tecmint@rocky-8 ~]$
```

Next, we will create a new group for our secure samba share and add the new samba user.

```
groupadd smb_group  
usermod -g smb_group smbuser
```

Thereafter, create yet another samba share which will be securely accessed. In our case, we have created another directory in the same path as the

```
mkdir -p /srv/tecmint/private
```

Then configure the file permissions for the samba share

```
chmod -R 770 /srv/tecmint/private  
chcon -t samba_share_t /srv/tecmint/private  
chown -R root:smb_group /srv/tecmint/private
```

Once again, access the Samba configuration file.

```
$ sudo vim /etc/samba/smb.conf
```

Add these lines to define to secure samba share.

```
[Private]  
path = /srv/tecmint/private  
valid users = @smb_group  
guest ok = no  
writable = no  
browsable = yes
```


Save the changes and exit.

Finally, restart all the samba daemons as shown.


```
systemctl restart smb;systemctl restart nmb
```

When you access your server this time around, you will notice an additional '**Private**' folder. To access the folder, you will be required to authenticate with the Samba user's credentials. Provide the username and password of the user you created in the previous step and click '**OK**'.

Samba User Authentication



Samba Private Share Directory



Step 5: Accessing Samba Share from Linux Client


To access the share from a Linux client, first, ensure that the Samba client package is installed.

```
$ dnf install -y samba-client
```

Then use the **smbclient** command as follows

```
smbclient '\\2.168.43.121\\private' -U smbuser
```

Access Samba Share from Linux

```
[james@rocky-8 ~]$  
[james@rocky-8 ~]$ smbclient '\\192.168.43.121\\private' -U smbuser  
Enter WORKGROUP\\smbuser's password:  
Try "help" to get a list of possible commands.  
smb: \>  
smb: \> ls  
.  
..  
36682240 blocks of size 1024. 23871400 blocks available  
smb: \> 
```

And this concludes this guide on setting up **Samba** on **RHEL**, **CentOS Stream**, **Rocky Linux**, and **AlmaLinux**. Your feedback on this guide will be highly appreciated.

Some taken from <https://www.tecmint.com/install-samba-rhel-rocky-linux-and-almalinux/>

Linux - Setup Rocky 9 SMTP Server

System Configuration

Upgrade Current System

```
dnf install epel-release -y
dnf upgrade -y
```

Configure SELinux

```
setenforce 0
sed -i 's/^SELINUX=.*/SELINUX=disabled/g' /etc/selinux/config
```

Disable Firewall

```
systemctl disable firewalld.service
```

Install Core Tools

```
dnf install bind-utils bzip2 cups cifs-utils enscript ftp gdb ghostscript java-1.8.0-openjdk-headless java-11-openjdk-headless krb5-workstation ksh lftp lrzsz lsof libnsl lzop mariadb-server mlocate mutt ncompress net-tools net-snmp net-snmp-utils net-tools nfs-utils nmap nvme-cli openldap-clients openssh-clients psmisc realmd rsync samba-client strace sysstat tcpdump telnet telnet-server tmux unix2dos vim vim-enhanced vsftpd wget xfsdump vsftpd htop mc rsyslog rsyslog-doc postfix dbus-daemon s-nail dovecot -y
```

Configure Virtual Tool


```
dnf install open-vm-tools -y  
sysctl vm.swappiness=10
```

Time Sync

```
systemctl enable --now chronyd
```

Configure Postfix

Postfix Settings

We now have to configure Postfix. One thing to keep in mind is that we're configuring Postfix to only send email, not receive it (as that is a far more complicated topic that requires considerable setup time and understanding to prevent the server from becoming an open relay, which could lead to a serious spam issue). Because of this, we can skip setting up Postfix to listen and instead go right to the hostname.

The Postfix hostname must be set to match the system hostname. We'll use the mail.example.com address (so make sure to change this to match your hostname). Set that hostname with the command:

```
sudo postconf -e "myhostname = mail.yourdomain.com"
```

Make sure to check that the apex domain (aka root domain) is correct with the command:

```
postconf mydomain
```

The apex domain for our example should be listed as <http://example.com> . If not, set it with:

```
sudo postconf -e "mydomain = example.com"
```

Set the myorigin parameter with:

```
sudo postconf -e "myorigin = $mydomain"
```

Set to allow all IP to access the server with:

```
sudo postconf -e "inet_interfaces = all"
```

Set to only allow IPv4 to use this server with:

```
sudo postconf -e "inet_protocols = ipv4"
```

Set the mydestination parameter with:

```
sudo postconf -e "mydestination = $myhostname, localhost.$mydomain, localhost, $mydomain"
```

Set the allowed IP address to relay on this server with:

```
sudo postconf -e "mynetworks = 127.0.0.0/8, 10.0.0.0/24, 192.168.0.0/16"
```

Set the mail folder with:

```
sudo postconf -e "home_mailbox = Maildir/"
```

Set the banner with:

```
sudo postconf -e "smtpd_banner = $myhostname ESMTP"
```

Set to disable verify with:

```
sudo postconf -e "disable_vrfy_command = yes"
```

Set to require the HELO for senders with:

```
sudo postconf -e "smtpd_helo_required = yes"
```

Set the message limit for example 10MB with:

```
sudo postconf -e "message_size_limit = 10240000"
```

Set SMTP Authentication with:

```
sudo postconf -e "smtpd_sasl_type = dovecot"
sudo postconf -e "smtpd_sasl_path = private/auth"
sudo postconf -e "smtpd_sasl_auth_enable = yes"
sudo postconf -e "smtpd_sasl_security_options = noanonymous"
sudo postconf -e "smtpd_sasl_local_domain = $myhostname"
sudo postconf -e "smtpd_recipient_restrictions = permit_mynetworks, permit_auth_destination,
permit_sasl_authenticated, reject"
```

With these taken care of, restart Postfix with:

```
sudo systemctl restart postfix
```

Extra Authentications

Configure additional settings for Postfix if you need.

It's possible to reject many spam emails with the settings below.

However, you should consider to apply the settings, because sometimes normal emails are also rejected with them. Especially, there are SMTP servers that forward lookup and reverse lookup of their hostnames on DNS do not match even if they are not spammers.

```
sudo postconf -e "smtpd_client_restrictions = permit_mynetworks, reject_unknown_client_hostname, permit"
sudo postconf -e "smtpd_sender_restrictions = permit_mynetworks,
reject_unknown_sender_domain, reject_non_fqdn_sender"
sudo postconf -e "smtpd_helo_restrictions = permit_mynetworks,
reject_unknown_hostname, reject_non_fqdn_hostname, reject_invalid_hostname, permit"
```

Enable Postfix

```
sudo systemctl enable --now postfix
```

Configure Dovecot

Dovecot Settings

This example shows to configure to provide SASL function to Postfix.

vi /etc/dovecot/dovecot.conf and uncomment and if not use IPv6, remove [::]

```
listen = *, ::
```

vi /etc/dovecot/conf.d/10-auth.conf and uncomment and change for the case you allow plain text auth

```
disable_plaintext_auth = no
```

and then add login to

```
auth_mechanisms = plain login
```

vi /etc/dovecot/conf.d/10-mail.conf and uncomment and add

```
mail_location = maildir:~/Maildir
```

vi /etc/dovecot/conf.d/10-master.conf and uncomment and add like follows Postfix smtp-auth

```
unix_listener /var/spool/postfix/private/auth {  
  mode = 0666  
  user = postfix  
  group = postfix  
}
```

vi /etc/dovecot/conf.d/10-ssl.conf and change to use SSL if available but not require SSL

```
ssl = yes
```

Enable Dovecot

```
sudo systemctl enable --now dovecot
```

Test the setup

Now that everything is set up, test Postfix by sending an email from the command line like so:

```
echo "Rocky Linux Rocks" | sendmail EMAIL
```

Where EMAIL is a valid email address.

If you receive the email, congratulate yourself on a job well done. If the email fails to arrive, you might need to verify if your DNS records are correct and the changes have taken effect (they can take up to 24 hours). You can also check the maillog with a command like:

```
tail -f /var/log/maillog
```

With the tail running, open another terminal window and attempt to send another email to see what kind of logs are written. From that information, you can start troubleshooting any issues that are causing problems.

Used ref from

https://www.server-world.info/en/note?os=Rocky_Linux_8&p=mail&f=1

https://www.server-world.info/en/note?os=Rocky_Linux_8&p=mail&f=2